


OBS Studio 28+


OBS Studio 28.0.0 and newer have obs-websocket support included in the firmware, so there is not need for downloading an additional support file for OBS. However, if you are using an older version of OBS Studio, please make sure you have downloaded the proper websocket support for your computer running OBS: <https://github.com/obsproject/obs-websocket>

OBS Studio Settings

Within OBS Studio there are a few settings to configure under Tools/WebSocket Server Settings




1. Under Plugin Settings, Enable WebSocket Server.
2. Under Server Settings, set the Server Port number (the default port is fine, just make note of the port number)
3. Also under Server Settings, Enable Authentication if desired and set Server Password if desired.



Skaarhoj Device Settings

On the Home Page, add OBS as a device manually. For OBS Studio 28 and newer, select Websocket 5.



Within the device details:

1. Input the IP address of the OBS computer
2. Input the Port number set in the OBS Websocket Server Settings

3. Select Authentication Enabled if you enabled it in OBS
4. Input password if you set one in OBS

OBS - Websocket 5
WebSocket 5 for OBS 28, 29, 30 and newer

Active

Name

Device Id

Model Id

Description

IP
IP address of the WebSocket server

Port
WebSocket server port. Default: 0 (auto detect by model)

Authentication Enabled
Enable authentication

Password
WebSocket server password

Confirm Connection

Once the information has been input, there should be a green Connected status in the device details on the Skaarhoj Home page.


OBS Studio

Websocket 5

Address: 192.168.11.138
Device ID: 1


Connected

Within the WebSocket Server Settings in OBS, you should also see the IP address for your Skaarhoj panel under the Connected WebSocket Sessions.



Additional Information

By default, Preview selections with not work within OBS unless you have selected Studio Mode. Once selected, Preview and Program will work as expected.



Revision #1

Created 4 June 2024 06:35:43 by Heather Pedersen

Updated 27 April 2026 10:55:50 by Heather Pedersen